


Windows Media Player Security Upgrade

For First Time Users

What is the Windows Media Player Security Upgrade?

Windows Computers: First-time users of OverDrive Media Console will be prompted to complete a one-time security upgrade for Windows Media Player.

Follow the prompts to complete the upgrade.





- Media Library
- View All Media
- My Collections

Welcome to OverDrive Media Console

Acquired: 7/29/2011
Last played: never
Expires: never
Duration: 03:56

Format: WMA Audiobook

OverDrive Media Console

i Your Windows Media Player requires a security upgrade to play protected content.

To upgrade the security of your Windows Media Player, make sure you are connected to the Internet and click 'OK'.

Note: If you have trouble or receive a connection error, please check your Firewall or Internet Security software to confirm that both OverDrive Media Console and Windows Media Player can access the Internet. The security upgrade may also be run in Internet Explorer at the following page:
<http://drmlicense.one.microsoft.com/indivsite>

Press the F1 key for more information.

OK Cancel

First Time Download of Audio Book – Windows Media Player Security Upgrade Message

The screenshot displays the OverDrive Media Console interface. At the top, there is a menu bar with 'File', 'View', 'Tools', and 'Help'. Below the menu bar is a toolbar with icons for 'Play', 'Transfer', 'Burn', 'Download', 'Delete', 'Properties', and a help icon. On the left side, there is a 'Media Library' section with options for 'View All Media' and 'My Collections'. The main area shows a blue header for 'Welcome to OverDrive Media Console' with details for an audio book: 'Format: WMA Audiobook', 'Acquired: 7/29/2011', 'Last played: never', 'Expires: never', and 'Duration: 03:56'. In the center, there is a 'Get Media' dialog box for 'Montana Library2Go' with the following details: Title: 1984, Format: WMA Audiobook, and Folder: C:\Users\Bobo\Documents\My Media\WMA Audiobooks. A 'Browse...' button is visible next to the folder field. In the foreground, an 'OverDrive Media Console' error dialog box is displayed with a yellow warning icon and the following text: 'Unable to acquire a license to play the selected title. The selected title requires a newer version of the Windows Media Player security upgrade (2.5.0.1) than is currently installed (2.5.0.0). Please upgrade the security of your Windows Media Player by selecting "Tools > Windows Media Player Security Upgrade..." from within OverDrive Media Console.' An 'OK' button is located at the bottom right of the error dialog.

OverDrive Media Console Help Menu for: Windows Media Player Security Upgrade

The screenshot shows a help window titled "Help" with a search bar and navigation buttons (Hide, Back, Print, Options). The main content area is titled "OverDrive Media Console - Windows Media® Player Security Upgrade". It contains a table of contents on the left and a main text area on the right. The table of contents lists various topics, including "Getting Started with OverDrive Media Console", "OverDrive Media Console Shortcut Keys", "Windows Media Player Security Upgrade", "Copyrighted Materials Notice", "Software License Agreement", "Media Explorer", "Main Menu", "Toolbar", "Left Tree View", "Right List View", "Status Bar", and "Dialog Boxes". The main text area provides instructions for performing a security upgrade, including a note about re-upgrading, a warning about connection errors, and step-by-step instructions for Windows Media Player 11 (or newer) and Windows Media Player 9 or 10.

OverDrive Media Console - Windows Media® Player Security Upgrade

The Windows Media Security Upgrade is a one-time process that must be performed before Microsoft® Windows Media Player will allow DRM (Digital Rights Management)-protected files to be played. A security measure, the security update identifies the copy of Windows Media Player with the computer on which Windows Media Player is being used.

Note that once you complete this process, you can re-upgrade Windows Media Player security at any time. Simply connect to the Internet and go to *Tools > Windows Media Player Security Upgrade...* in OverDrive Media Console.

If you have trouble or receive a connection error while completing these steps, please check your Firewall or Internet Security software to confirm that both OverDrive Media Console and Windows Media Player can access the Internet. The security upgrade may also be run in Internet Explorer at the following page: <http://drmlicense.one.microsoft.com/indivsite>.

The steps taken to complete this one-time task vary depending on the version of Windows Media Player installed on your computer.

If you have Windows Media Player 11 (or newer)...

1. While connected to the Internet, open OverDrive Media Console.
2. Go to *Tools > Windows Media Player Security Upgrade...*
A dialog box is displayed, notifying you that Windows Media Player requires a security upgrade to play DRM-protected content.
3. Click 'OK' in the dialog box.
Windows Media Player opens and the 'Windows Media Player' dialog box is displayed.
4. Click 'Upgrade' to download and install the required security component.
Windows Media Player indicates that it is 'Connecting to server...'. Once connected, the security component is downloaded and installed. Windows Media Player indicates that the security component was upgraded successfully.
5. Click the 'Close' button in the 'Windows Media Player' dialog box.
The 'Media Usage Rights Acquisition' dialog box is displayed.
6. Click the 'Play' button in the 'Media Usage Rights Acquisition' dialog box to complete the upgrade.
Windows Media Player plays a brief file, confirming that you have completed the upgrade.
7. Click the 'Cancel' button to close the 'Media Usage Rights Acquisition' dialog box. If desired, you can also close Windows Media Player at this time.
You have successfully completed the Windows Media Player Security Upgrade.

If you have Windows Media Player 9 or 10...

1. While connected to the Internet, open OverDrive Media Console.
2. Go to *Tools > Windows Media Player Security Upgrade...*
A dialog box is displayed, notifying you that Windows Media Player requires a security upgrade to play DRM-protected content.
3. Click 'OK' in the dialog box.
Windows Media Player opens and the 'Windows Media Player' dialog box is displayed.
4. Click 'Yes' to perform the upgrade.
The 'License Acquisition' dialog box is displayed, indicating that you have installed the Windows Media Player Security Upgrade.
5. Click the 'Play' button in the 'License Acquisition' dialog box to complete the upgrade.
Windows Media Player plays a brief file, confirming that you have completed the upgrade. If desired, you can also close Windows Media Player at this time. You have successfully completed the Windows Media Player Security Upgrade.